


## Running DFM-Fitting Code in JupyterLab Online Demo

1. Download “DFM Jupyter NB.ipynb”, “Template\_PK\_data.xlsx”, and “Template\_TUMOR\_data.xlsx” files from <https://github.com/mlim0789/DFM-Fitting>
2. We will verify the code using example data. In the template PK and Tumor data files, copy and paste values from Example Sheet to Sheet 1. Save files.

*Excel sheet after copying and pasting Example PK values:*



Time (hr)	Conc. values:	St. Dev. Values:
5.00E-01	3.63E-01	2.62E-02
3.00E+00	2.89E-01	1.48E-02
6.00E+00	2.68E-01	6.10E-03
2.40E+01	1.75E-01	1.22E-02
4.80E+01	9.92E-02	0.00E+00

3. Click on the following link to launch JupyterLab demo:

<https://mybinder.org/v2/gh/jupyterlab/jupyterlab-demo/try.jupyter.org?urlpath=lab>

4. The loading page will appear as the interactive development environment is being set up

Give us feedback on how mybinder.org is doing and what to improve: [the mybinder.org user survey](https://mybinder.org/user-survey) (it is only three questions!). Thank you!



Starting repository: [jupyterlab/jupyterlab-demo/try-jupyter.org](https://github.com/jupyterlab/jupyterlab-demo/tree/master/try-jupyter.org)


Need more than just a Jupyter notebook? You can customize the user interface.

Build logs


SHOW

## 5. You may see a demo notebook appear, or just the launcher landing page


### Demo notebook:




### Launcher page:



6. Either way, upload your files by clicking on the arrow icon:




7. After uploading the JupyterLab notebook, and PK & TUMOR data files, they will appear on the left panel. Click on the “DFM Jupyter NB” file:



8. When you scroll down, you’ll see grey boxes, which are cells containing executable codes. Hitting Shift+Enter will run the code.

Square brackets on the left side indicate the status of running the code. When it is empty, it has not been run. While running, it will display “[ \* ]”, and when it is finished, a number pops up. Any outputs will be shown below the cell.



9. First, there are code packages that need to be installed. Run the command for installing openpyxl and tabulate, and you should see an output like this from each command:

## Install required packages:

```
[ ]: # Hit Shift+Enter to run this cell & subsequent cells

[1]: pip install openpyxl

Collecting openpyxl
  Downloading https://files.pythonhosted.org/packages/95/8c/
  |████████████████████████████████████████| 174kB 3.4MB/s eta 0:
Collecting jdcal (from openpyxl)
  Downloading https://files.pythonhosted.org/packages/f0/da/
  hl
Collecting et_xmlfile (from openpyxl)
  Downloading https://files.pythonhosted.org/packages/22/28/
Building wheels for collected packages: openpyxl, et-xmlfile
  Building wheel for openpyxl (setup.py) ... done
```

10. Next, enter file paths for the PK and tumor data. You'll need the current file directory. For this JupyterLab demo, it'll likely be `"/home/jovyan/demo"`

## Enter File Paths for PK and Tumor data workbooks:

```
[3]: # Obtain Current File Directory

import os
print(os.getcwd())

/home/jovyan/demo
```

11. Replace the filepaths for `load_workbook` command accordingly. Ensure there are **no excess spaces** between the single quotation marks at the end!

*Before replacing filepath:*

```
[ ]: from openpyxl import load_workbook

# Put relative filepath to PK data excel file here:

book = load_workbook('filepath/filename1.xlsx') # REPLACE "filepath/filename"
# example: /home/jovyan/demo/Template_PK_data.xlsx
```

*E.g. After replacing filepath:*

```
book = load_workbook('/home/jovyan/demo/Template_PK_data.xlsx')
# example: /home/jovyan/demo/Template_PK_
```

12. If you see an error like these, double check that there are no excess spaces between the filepath quotes, and that the file name has been entered correctly

```
-----
InvalidFileException                                Traceback (most recent call last)
<ipython-input-10-ffbdcd476667> in <module>
      3 # Put relative filepath to PK data excel file here:
      4
----> 5 book = load_workbook(' /home/jovyan/demo/Template_PK_data-TEST.xlsx
      6                               # example: /home/jovyan/demo/Template_PK_dat
      7

/srv/conda/envs/notebook/lib/python3.7/site-packages/openpyxl/reader/excel.p
  311     """
  312     reader = ExcelReader(filename, read_only, keep_vba,
  313                           data_only, keep_links)
```

•  
•  
•

```
InvalidFileException: openpyxl does not support .xlsx file format, please check you
can open it with Excel first. Supported formats are: .xlsx,.xlsm,.xltx,.xltm
```


```
FileNotFoundError: [Errno 2] No such file or directory: ' /home/jovyan/demo/Template
_PK_data-TEST.xlsx'
```

13. Run the commands for verifying PK and tumor data loading. You should see an output like this, which should match values on the Excel file.

```
counter = counter + 1                                #cycle to next TUMconc column 'counter' before
print("PK error arrays: ",PKErrArr)
```

```
Series: ['3HM (C18)', '3HM (C16)']
PK time arrays: [0.5, 3, 6, 24, 48]
PK concentration arrays: [[0.3626376767037034, 0.28935300158026434, 0.2683652440186
6785, 0.17469072931974827, 0.09919417577214619], [0.35827663852525005, 0.23878920992
922595, 0.19600462396468077, 0.08053746210746987, 0.03903860887530659]]
PK error arrays: [[0.026155791999999997, 0.014820395999999998, 0.006102524, 0.01220
2939999999999, 0.012202939999999999], [0.020053268, 0.014820395999999998, 0.00435894
96, 0, 0]]
```

14. Run the code for fitting PK data, and you should see an output that looks like this




	3HM (C18)	3HM (C16)
C0	0.43042	0.407854
beta	0.281396	0.397448
K1	1.50796	0.640804
K2	0.0237371	0.0430696
R^2	0.999997	0.998278

Standard deviations:


	3HM (C18)	3HM (C16)
C0	0.0100995	0.0295186
beta	0.0159962	0.0572274
K1	0.172918	0.384638
K2	8.54976e-05	0.00680832

15. Note that the graph and table output values have been automatically saved as PNG image (Fig-PK.png) and .xls worksheet files, available on the left panel! You can open and download these.





16. Now that the PK values have been successfully fitted, we can perform the actual DFM fit on tumor accumulation data.

Run the code for DFM Fitting. You should see the following output, with figure and table files saved to the left panel accordingly. Effective permeability data table is saved as "Peff\_output.xls"



	3HM (C18)	3HM (C16)
alpha	0.147158	0.222045
beta	0.281396	0.397448
Peff	1.45034	1.86288
SD	0.41845	0.401891
%SD	28.8518	21.5736

17. Finally, run the code to generate residuals of the fit for each series



18. If you see all of the above outputs, congratulations, the DFM fitting code has run successfully!
19. Next, replace the PK and Tumor data with your values in the Excel template Sheet 1, and repeat the PK & DFM fitting process to extract effective permeability values for your system.

Thank you for your interest in our work. We sincerely hope that this method serves as a valuable tool to complement your cancer nanomedicine research. If you have any questions, comments, or suggestions, please direct them to Marc Lim at [mlim0789\[at\]gmail.com](mailto:mlim0789[at]gmail.com) ([ResearchGate](#), [LinkedIn](#)); or Professor Ting Xu at [tingxu\[at\]berkeley.edu](mailto:tingxu[at]berkeley.edu) (UCB [Faculty profile](#)).